Extraplanetary Launchpads

User's and Modder's Guide

Bill Currie (taniwha)



Introduction

Building bases and space stations in Kerbal Space Program can be fun and rewarding on its own: they look good and allow for the production or storage of fuel and science, but they amount to little more than outposts. One main problem with such outposts is that when things go wrong and repairs are needed, they are highly dependent on resupply runs from the KSC¹. A bigger problem is they serve only as way stations for grand missions: it is very difficult to use them as the origin of such missions as all the vessels comprising the grand mission must be launched from the KSC.

Extraplanetary Launchpads (or EL for short²) gives additional meaning to planetary bases and orbiting space stations by allowing for the construction of all manner of vessels away from the KSC. The construction can be carried out both on the surface of any body and in orbit. However, EL does not do anything for life support supplies (other mods have that covered), or the expansion of the kerbal population at the base or station.

EL defines the resources³ used in the construction of vessels, and provides the parts required to obtain and process those resources into the final product: a vessel that can be an independent ship (or other vehicle), base, station, a module for a larger vessel, or even individual parts⁴.

¹Kerbal Space Center? Kerbin Space Center? Kerman Space Center? Kraken Snack Constructor? ²Just like "extraterrestrial", "extraplanetary" is (or would be) one word, and "launchpad" is also one word, thus in this case TLA is Two Letter Acronym.

³Other mods can define other resource that replace those defined by EL.

⁴Though currently a little awkwardly.

С	on	tei	nts
-	••••		

Lis	List of Figures							
Lis	st of	Tables		5				
I.	Us	ing Ext	traplanetary Launchpads	6				
1.	Gett	ting Sta	irted	6				
	1.1.	Install	ation	6				
		1.1.1.	Minimal Installation	6				
		1.1.2.	Survey Build Support	6				
		1.1.3.	Recommended Mods	6				
		1.1.4.	Mods that support or use EL	7				
	1.2.	Setup		7				
2.	Con	structio	n Basics	7				
	2.1.	Resour	Ces	7				
		2.1.1.	Prospecting and Mining: dirt? to METALORE	7				
		2.1.2.	Smelting: METALORE to METAL	8				
		2.1.3.	Working: METAL to ROCKETPARTS	11				
		2.1.4.	Remelting: SCRAPMETAL to METAL	11				
		2.1.5.	Building: ROCKETPARTS to ROCKETS	11				
		2.1.6.	Recycling: ROCKETPARTS to SCRAPMETAL	11				
	2.2.	Produ	etivity	11				
	2.3.	Constr	uction Skill	12				
		2.3.1.	Unskilled kerbals	12				
		2.3.2.	Non-career modes	13				
	2.4.	Works	hops	13				
		2.4.1.	Fully equipped	13				
		2.4.2.	Other parts	13				
	2.5.	Pads .	•••••••••••••••••••••••••••••••••••••••	13				
		2.5.1.	Launchpads and Orbital Docks	13				
		2.5.2.	Survey Stations and Survey Stakes	14				
		2.5.3.	Micro-Pad	14				
3.	Surv	vey Syst	tem	14				
	3.1.	Survey	Station	15				
		3.1.1.	Survey Skill	15				
	3.2.	Survey	Site	15				
4.	Desi	igning a	a construction capable vessel	17				
-	4.1.	Orbita	l Construction	17				

	4.2.	Grounded Construction	19
		4.2.1. The Base Kraken	20
	4.3.	Roughing It	22
11.	Мо	odding Extraplanetary Launchpads	23
5.	Con	figuration	23
	5.1.	Part Modules	23
		5.1.1. ELControlReference	23
		5.1.2. ELConverter	23
		5.1.3. ELDisposablePad	26
		5.1.4. ELExtractor	$\frac{-0}{26}$
		5.1.5. ELLaunchpad	27
		5.1.6. ELNoControlSwitch	$\frac{-}{28}$
		5.1.7. ELBecycler	$\frac{-0}{28}$
		5.1.8 ELSurveyStake	29
		5.1.9 ELSurveyStation	29
		5.1.10 ELTarget	30
		5.1.10. Elimaget	30
	5.2	Recipes	31
	0.2.	5.2.1 Becipes for Building	32
		5.2.1. Recipes for Bunding	34
		5.2.3 Becipes for Converting	35
		5.2.4 Other Becipes	37
	53	Besource Bates	37
	0.0.		51
6.	EL /	ΑΡΙ	38
	6.1.	Interfaces	38
		6.1.1. ELBuildControl.IBuilder	38
		6.1.2. ELControlInterface	38
		6.1.3. ELWorkNode	38
		6.1.4. ELWorkSink	38
		6.1.5. ELWorkSource	39
		6.1.6. IResourceProvider	39
	6.2.	Part Modules	39
		6.2.1. ELControlReference	39
		6.2.2. ELConverter	39
		6.2.3. ELDisposablePad	39
		6.2.4. ELExtractor	39
		6.2.5. ELLaunchpad	39
		6.2.6. ELNoControlSwitch	39
		6.2.7. ELRecycler	39
		6.2.8. ELSurveyStake	39
			50

References								40																	
	6.3.1.	ELVessel	Workl	Vet		•	•	 •	•	•	 •	•	•	• •	•	•	•	•	 •	•	•	•	•	•	39
6.3.	Vessel	Modules								•		•	•		•			•				•		•	39
	6.2.11.	ELWorks	hop									•			•		•	•							39
	6.2.10.	ELTarget										•			•		•	•							39
	6.2.9.	ELSurve	yStatio	on											•										39

List of Figures

1.	Resource flow chart
3.	Orbital Dock
4.	Micro-Pad
2.	Hillside survey site, somewhere on Minmus
5.	Gilly Base

List of Tables

1.	Comparison of	of stock KSP	LFO engines.		10
----	---------------	--------------	--------------	--	----

Part I. Using Extraplanetary Launchpads

1. Getting Started

1.1. Installation

1.1.1. Minimal Installation

Download the zip file for the latest version via the EL forum threadtaniwha n.d.(b) and extract its contents to KSP's GameData directory⁵. Ensure that the latest version of Module ManagerSarbian n.d. is installed correctly.

Note that the minimal installation will not support survey builds.

1.1.2. Survey Build Support

In order to support survey builds, Kerbal Inventory SystemIgorZ n.d.(b) is required.

1.1.3. Recommended Mods

There are several mods that improve EL:

- **Diamond Grid Trusses and Containerstaniwha n.d.(a)** Truss and tank segments based off truncated triangles.
- Kerbal Alarm ClockTriggerAu n.d. Keep track of when a build will be finished. Really, the most important mod for anybody wishing to run multiple missions in parallel, and useful even for those who run only one mission at a time.
- KerbalStatstaniwha n.d.(e) Provides a means to extend kerbal attributes, but in the context of EL it provides time and activity based experience for kerbals.
- **Kethanetaniwha n.d.(f)** The original ISRU solution for KSP. Provides hot-spot⁶ mining of METALORE.
- Modular Fuel Tankstaniwha n.d.(g) Edit tank resources in the editor.
- Talisar Partstaniwha n.d.(h) High capacity spherical tanks (up to over $200m^3$) and various structural parts.

Kerbal Attachment SystemIgorZ n.d.(a) Pipes and winches.

TAC Fuel BalancerZ-Key Aerospace n.d. Easier transferal of resources.

⁵Ok, folder. Now get off my lawn ;)

 $^{^6{\}rm Areas}$ where resource extraction is done at 100% of extractor capacity. Other areas (those covered by the stock resource system) get 1% to 15% extraction rate.

1.1.4. Mods that support or use EL

Kerbal Planetary Base SystemsNils277 n.d. Several new parts that are designed to be used in a planetary base for the kerbals.

PathfinderAngel-125 n.d. Space Camping & Geoscience.

SimpleConstuctionRealGecko n.d. Uses EL but stock parts.

1.2. Setup

The first time the space center scene is entered, an options window will be presented allowing for the selection of various settings:

- Use of Blizzy's toolbar when available.
- Creation of KAC alarms and the default action for those alarms.
- Visibility of the build resources window in the editors.
- Whether "craft hulls" are presented during build.
- Debug output for craft hulls. Generally not needed unless things go wrong in generating a hull, then the data will be requested.

2. Construction Basics

2.1. Resources

Currently, EL uses four resources for its production chain (though the recipe system (see section 5.2 on page 31) allows for much more complicated systems).

- **MetalOre** Assumed to be hematite⁷ (but not explicitly stated as such) and thus has a density of $5.2t/m^3$.
- **Metal** Assumed to be iron (but not explicitly stated as such) and thus has a density of $7.8t/m^3$.
- **RocketParts** Assumed to be sub-parts ready for assembly into actual parts, and thus has a very low density of $0.5t/m^3$.
- **ScrapMetal** The true product of any machine shop: all machine shops produce scrap metal in various forms and efficiencies. The lumps of metal handed over to the customer are really the left-overs from producing scrap metal. Scrap metal generally does not pack well, though better than parts, so a density of $0.8t/m^3$ was chosen as an average.

2.1.1. Prospecting and Mining: dirt? to MetalOre

⁷A common form of iron ore.

In order to obtain METALORE when away from the KSC, one of the augers is used to mine METALORE from the surface of the planet or moon. EL uses the stock resource distribution system configured to distribute METALORE, so prospecting is done as for stock's ORE resource, but with a focus on METALORE instead.

Kethane and Karbonite Prior to KSP 1.0, EL relied solely on Kethanetaniwha n.d.(f) for its prospecting and mining, and there was an adaptation to make EL use Karboniterabidninjawombat n.d. instead.

As of KSP 1.0 (EL 5.1.90) Kethane is completely optional, but if present, will be used on top of the stock resource system. Scanning is quite separate, but mining is done using the exact same augers. Mining outside a METALORE deposit created by Kethane will extract METALORE at the rate dictated by the concentration given by the stock system (1% to 15%), but deposits created by Kethane effectively provide hot-spots of 100% concentration.

The Karbonite adaptation seems to have been mothballed, but it was mostly a parts mod with configs for EL, so it may still be usable.

2.1.2. Smelting: MetalOre to Metal

METALORE is converted to METAL via smelting. Smelting is the process of reducing⁸ metal oxides. EL assumes MET-

ALORE is Fe_2O_3 (the most common iron ore on Earth). Reducing Fe_2O_3 is a three-step process (from Wikipedia):

Stage One $3Fe_2O_3 + CO \rightarrow 2Fe_3O_4 + CO_2$

Stage Two $Fe_3O_4 + CO \rightarrow 3FeO + CO_2$

Stage Three $FeO + CO \rightarrow Fe + CO_2$



Figure 1: Resource flow chart

⁸Chemistry term, the opposite of oxidizing (or reduction vs oxidization).

However, this really happens all at once in a smelter so the effective process is:

 $3\text{Fe}_2\text{O}_3 + 9\text{CO} \rightarrow 6\text{Fe} + 9\text{CO}_2.$

Fe has a molar mass of 55.845g/mol, O has a molar mass of 15.9994g/mol, so 479.0646g of Fe₂O₃ will produce 335.070g of Fe. This leads to a METALORE to METAL mass conversion rate of 0.6994255^9 .

In order to model the CO consumption, EL assumes that LiquidFuel is RP-1 ($C_{12}H_{16}$) and that Oxidizer is liquid oxygen (O₂). The stoichiometric equation for burning RP-1 is:

 $C_{12}H_{16} + 16O_2 \rightarrow 12CO_2 + 8H_2O$

However, rockets tend to burn rich (reduced oxidizer quantity) in order to avoid oxidizing the engine, keep the engine cooler, and increase the number of lighter molecules in the exhaust. KSP's standard LIQUIDFUEL and OXIDIZER mix of 9:11 by volume very closely approximates the following when LIQUIDFUEL is assumed to be RP-1 and OXIDIZER is assumed to be liquid oxygen¹⁰ (used for 0% efficient smelting):

 $2C_{12}H_{16} + 17O_2 \rightarrow 2C + 17CO + 4CO_2 + CH_2O + 7H_2 + 8H_2O$

The resulting equation for 100% efficient¹¹ smelting thus becomes:

 $10Fe_2O_3 + 2C_{12}H_{16} + 17O_2 \rightarrow 20Fe + 24CO_2 + 16H_2O$

 $C_{12}H_{16}$ has a molar mass of 160.25544g/mol, CO_2 has a molar mass of 44.0095g/mol, H_2O has a molar mass of 18.01528g/mol, C 12.0107g/mol, CO 28.0101g/mol, CH_2O 30.02598g/mol, H_2 2.01588g/mol. Thus the two equations become the following when viewed as masses:

 $320.51088 + 543.9796 \rightarrow 24.0214 + 476.1717 + 176.038 + 30.02598 + 14.11116 + 144.12224$

 $1596.882 + 320.51088 + 543.9796 \rightarrow 1116.9 + 1056.228 + 288.24448.$

The mass conversion rate of METALORE to METAL is still 0.6994255.

Smelting is assumed to consume 8.62MJ/kg of produced METALR.J. Fruehan n.d.

The combustion of LIQUIDFUEL and OXIDIZER is assumed to produce 6MJ/kg. The justification for this comes from analyzing the properties of KSP's stock LFO engines and noting that the Poodle (the most efficient) gets 5.9MJ/kg of LIQUIDFUEL and OXIDIZER (see table 1 on the next page).

Thus, EL's smelters nominally¹² consume 864.49048g/s of LIQUIDFUEL and OXIDIZER to produce 5186.94288kJ/s of heating along with the products necessary for smelting. At 100% efficiency, they consume 1596.882g/s of METALORE and 9627.678kJ/s of heat while producing 1116.9g/s of METAL. Thus 100% efficiency is unobtainable as there is insufficient heat supplied by the LFO mix. In theory, the attainable efficiency is a bit less than 53.9%, but due to transferred resources cooling the smelter¹³, the maximum

 $^{^{9}0.46628367}$ volume (resource unit) conversion rate.

¹⁰Note that the exact ratios of the products were arbitrarily chosen but are chemically "correct" (balanced), and that the inclusion of formaldehyde is the result of "Hmm, wonder if there's a CH_2O . Oh, there is, and it does appear in partial combustion of hydrocarbons. Neat."

¹¹Arbitrary assumption.

¹²The actual rates vary with the smelter: 800g/s, 3149.8g/s and 5000g/s of LFO, with the other rates scaled accordingly.

¹³And an engineering mistake in the smelter design. Some kerbals will miss out on snacks.

Engine	Thrust (N)	Isp(s)	Ve (m/s)	flow (kg/s)	power (W)	Esp (J/kg)
24-77	16k	290	2843.9	5.6	22.8M	4.0M
48-7S	20k	320	3138.1	6.4	31.4M	4.9M
aerospike	180k	340	3334.2	54.0	300.1M	5.6M
LV-1	2k	315	3089.1	0.6	3.1M	4.8M
LV-1R	2k	290	2843.9	0.7	2.8M	4.0M
LV-909	60k	345	3383.3	17.7	101.5M	$5.7\mathrm{M}$
LV-T30	240k	310	3040.0	78.9	$364.8 \mathrm{M}$	4.6M
LV-T45	215k	320	3138.1	68.5	$337.3 \mathrm{M}$	4.9M
mainsail	1500k	310	3040.0	493.4	2.3G	4.6M
Mk55	120k	305	2991.0	40.1	$179.5 \mathrm{M}$	4.5M
poodle	250k	350	3432.3	72.8	429.0M	$5.9\mathrm{M}$
SSME	1000k	315	3089.1	323.7	1.5G	4.8M
skipper	650k	320	3138.1	207.1	1.0G	4.9M
twin-boar	2000k	300	2942.0	679.8	2.9G	4.3M
rhino	2000k	340	3334.2	599.8	3.3G	$5.6\mathrm{M}$
mammoth	4000k	315	3089.1	1294.9	6.2G	4.8M
rapier	180k	305	2991.0	60.2	269.2M	4.8M
vernor	12k	260	2549.7	4.7	15.3M	3.3M

Table 1: Comparison of stock KSP LFO engines. Thrust and I_{sp} are from the config files. V_e (exhaust velocity) is $I_{sp} * g_0$ (9.8066). Flow is $\frac{thrust}{V_e}$. Power is $\frac{1}{2}thrust * V_e$. E_{sp} (energy per kg) is $\frac{power}{flow}$ or $\frac{1}{2}V_e^2$.

efficiency appears to be about 40%.

2.1.3. Working: Metal to RocketParts

METAL is converted to ROCKETPARTS by working it. Currently, this is done using either the workshop (big blue part in Utilities), or the workbench (tower with little platforms in Pods). Unfortunately, the process is quite bogus: METAL is used for for everything, and the conversion speed is probably too fast. However, the efficiency (0.7 by mass) is reasonable: it is the estimated average of various means of production: cutting cast iron parts leads to high efficiency, but cutting lumps of steel can lead to fairly low efficiency depending on just how much metal needs to be cut away. At the same time, SCRAPMETAL is produced at a rate of 0.295 by mass (some scraps are lost).

2.1.4. Remelting: ScrapMetal to Metal

SCRAPMETAL can optionally be remelted to METAL using a smelter. The process is lossless (conversion rate of 1), the loss (very small) occurs when producing the SCRAP-METAL. Storing and reclaiming SCRAPMETAL is fully optional: running out of storage will not stop METAL to ROCKETPARTS conversion.

2.1.5. Building: RocketParts to Rockets

Building is done by the launchpads, orbital dock, or survey station (or just "pads" for short). The rate is governed by the overall vessel productivity (measured in kerbalhours (Khr)) shared amongst active pads. Each ton of rocket (dry-mass) requires five kerbal-hours (i.e. 5Kh/t).

There have been discussions that EL's build rate is too high compared to Kerbal Construction Time, but those arguing that side were unaware that ROCKETPARTS represent components to be assembled into the parts visible in KSP. The building process is really just the kerbals putting those components together. It is the smelting and working stages that are unrealistically fast.

2.1.6. Recycling: RocketParts to ScrapMetal

Recycling is done on a part-by-part basis. When a part is recycled, it is first drained of any resources it contains (e.g., LIQUIDFUEL or OXIDIZER), and those resources will evaporate, be broken down into other resources to be reclaimed, or transferred and thus reclaimed depending on the resource (most will be transferred). Once the part has been drained, it will be broken down from ROCKETPARTS to SCRAPMETAL and the SCRAPMETAL reclaimed.

Of course, any reclaimed resource needs storage space. Otherwise, it will be lost.

2.2. Productivity

All kerbals have a base productivity score determined by their stupidity, courage, and bad-ass characteristics. The more stupid a kerbal is, the less that kerbal will contribute

Some of you may have had spotty results recycling entire vessels: that is intentional, and there is a way around it (see if you can guess). to the workshop's (and thus the overall vessel's) productivity, and more courageous kerbals will, in general, contribute less than less courageous kerbals, though bad-ass kerbals complicate the relationship. It is entirely possible for a kerbal to have negative productivity.

If the KerbalStatstaniwha n.d.(e) mod is installed, then the amount of time a kerbal has spent in certain workshops (currently only EL's blue workshop (afaik)) improves the kerbal's productivity.

A workshop's productivity is the sum of the productivities of all kerbals working in that shop. A vessel's productivity is the sum of the productivities of all workshops in that vessel. If the vessel's productivity is greater than zero, then construction will progress. Negative productivity does not cause production to become destruction, instead it causes a productivity deficit that must be overcome by better construction kerbals before construction will proceed.

2.3. Construction Skill

Kerbals with the construction skill (by default, engineers, but hereon referred to as construction kerbals) are the cornerstone of workshop productivity. However, their space-faring (stock) experience affects their productivity greatly.

- **0** stars The kerbal can work in a fully equipped workshop.
- 1 star The kerbal can work in any workshop.
- **2 stars** The kerbal is always productive in a fully equipped workshop (base productivity still matters, but to get negative productivity, the kerbal would have to have infinitely negative base productivity).
- **3** stars The kerbal is always productive in any workshop.
- **4 stars** The kerbal enables skilled workers in any workshop (a 4-star construction kerbal in an under-equipped workshop allows 0-star construction kerbals to contribute).
- **5 stars** The kerbal enables unskilled workers in a fully equipped workshop (a 5-star construction kerbal in a fully equipped workshop allows any kerbal, even those without the construction skill, to contribute).

2.3.1. Unskilled kerbals

Unskilled kerbals cannot work unless a 5-star construction kerbal is present in the same workshop, and the workshop must be fully equipped, but if the kerbal's experience level is 2 or less, and the kerbal's base productivity is negative, the kerbal will detract from the workshop's productivity.

2.3.2. Non-career modes

In sandbox (and science?) mode, all kerbals are level 5, so there will be no negative contributions, and if there is at least one construction kerbal in the workshop, then all kerbals of sufficient ability will contribute.

2.4. Workshops

Workshops, too, affect productivity. All workshops have a productivity factor that is multiplied by the sum of the productivities of the kerbals working in that shop. The resulting productivity is then passed to the vessel.

2.4.1. Fully equipped

Fully equipped workshops are those with a productivity factor of 1.0 or more, or specially marked workshops with lower productivity factors. EL's blue workshop, and the rocket workbench are both fully equipped workshops.

2.4.2. Other parts

All stock crewed parts act as under-equipped workshops. In addition, all crewed command pods, including those from other mods, act as under-equipped workshops. Many base-building mods (eg, KPBSNils277 n.d., PathfinderAngel-125 n.d.) provide workshops (refer to those mods for details).

2.5. Pads

All construction is done at "pads", whether the pad is an orbital dock, a launchpad, a survey site (marked out using survey stakes and managed by a survey station), or a micro-pad.

Initiating construction is the same for everything: open the build window (via either the toolbar button (blizzy's toolbarblizzy78 n.d., or the stock app button), or the Show UI button in the PAW¹⁴), select the craft to build, and press the Build button. Between selecting the craft to build and pressing the Build button, the required and optional resources for the build will be displayed in a preview. There is no need to have all the required resources on-hand when beginning the build: if they run out during the build, the build will stop until the resources become available and then automatically resume. The resources can become available via supply runs or local processing.

2.5.1. Launchpads and Orbital Docks

Technically, there is no difference between a launchpad and an orbital dock: they operate exactly the same way. The difference comes in the physical form of the parts: launchpads are optimized for grounded operation, and the orbital dock is optimized for orbital operation. For roleplay purposes, "fully equipped" be can thought of as the workshop having all the necessary tools, and the productivity factor as being the quality of the tools or the level of automation available.

¹⁴Part Action Window (right-click menu)

2.5.2. Survey Stations and Survey Stakes

Survey stations use local survey sites to specify the location and orientation of the built vessel. Survey sites are sets of one or more survey stakes with the same name and within range (200m) of each other.

2.5.3. Micro-Pad

The micro-pad is a single-use construction point. When the build is finalized, the pad self-destructs and the build is attached to the parent vessel as if the build had been placed there in the editor (VAB or SPH). Also, the micro-pad can be carried on a kerbal's back using KISIgorZ n.d.(b).

The orientation and position of the build is controlled by the combination of the orientation and position of the micro-pad, and the automatically selected attach node of the root part. The colored diamonds on the micro-pad indicate the orientation of the root part when its bottom node is selected (red = +X, blue = +Z, cyan = -X, yellow = $-Z^{15}$. It is important to remember that when the micro-pad is facing up, the root part's selected node will be facing down, having been rotated around the part's Z axis.

The micro-pad automatically selects the attach node of the root part by searching for the first available (unattached) node. First the bottom node is checked, then the top node, then any remaining nodes in the order they are found. Thus a small amount of control over which node is selected can be obtained simply by attaching parts to the undesired nodes.

3. Survey System

When landed, orbital docks can be awkward for building as they tend to be on top of the building vessel (especially awkward for building rovers as getting the rover to the ground can be an issue), and launchpads are highly sensitive to ground conditions, and and have their own issues when building large vessels. Also, they provide no flexibility in placement or orientation of the build.

EL's survey system greatly eases the seeding (or even complete build-out) of bases, and works equally well for building ships and other vessels. However, it does have one disadvantage: any optional resources (liquid fuel, oxidizer, electric charge, etc) will *not* be transferred: the build will be empty of such resources (freedom is not free), but as KISIgorZ n.d.(b) is required to place the stakes, and KASIgorZ n.d.(a) is almost always installed with it, this disadvantage should be only minor¹⁶.

The survey system consists of two parts¹⁷: the survey station, and the survey site. The survey station (a re-purposed hitchhiker can) is used to keep track of the survey

dename faults to the name of the kerbal who planted it with "Base" appended. Thus if VALENTINA plants а stake, it will named be VALENTINA KERMAN BASE. Thus, when creating а site consisting of more than one stake, it is easiest tohave only one kerbal do the stake planting. Also, if multiple local sites are desired. getting а different kerbal to plant the stakes for each site will make it

А

stake's

¹⁵Hopefully the colors are distinct enough that any suffering from colorblindness can distinguish at least one diamond. The pad's default orientation in the VAB is such that red (+X) points to the VAB door, blue (+Z) points to the north wall, cyan (-X) to the west and yellow (-Z) to the south.

 $^{^{16}\}mathrm{It}$ can, however, lead to good entertainment: 5th Horseman n.d.

¹⁷If you're thinking KSP parts, then it's three: survey station, survey stake, and mallet.

sites and do the actual building (it serves the same purpose as the orbital dock or a launchpad, but must be landed), and must be flown down to the surface in the vicinity of where the builds will occur. The survey site is ephemeral: it is marked out by one or more survey stakes and is used to specify the location and orientation of the build.

3.1. Survey Station

3.1.1. Survey Skill

Kerbals with the survey skill (by default, pilots, but hereon referred to as survey kerbals) affect the range of a survey station according to their stock experience level. The experience level of the most skilled survey kerbal in the survey station is used. However, even an unskilled kerbal can man a survey station, and an unmanned survey station is still operational.

unmanned 20 meters.

unskilled 50 meters.

0 stars 100 meters.

1 star 200 meters.

2 stars 400 meters.

3 stars 800 meters.

4 stars 1600 meters.

5 stars 2000 meters.

Note that the range is from the survey vessel's center of mass to the nearest stake of the survey site, but stakes may be separated by up to 200 meters¹⁸.

3.2. Survey Site

Stakes have two modes with seven settings in each mode (default is Direction:Origin):

Direction these are used to control the orientation of the build.

- **Origin** used to mark the location above which the build's root part will be placed, and also forms the reference point for other direction stakes that aren't in pairs.
- -X and +X used to specify the lateral (port (-X) and starboard (+X)) axis of the build (both VAB and SPH). If both -X and +X are used, then the origin is is ignored, otherwise the axis runs from -X to origin or origin to +X.

¹⁸This is a bit of a misfeature: the range should be from the survey station part and the maximum separation of the stakes should be dependent on the skill as well.

- -Y and +Y used to specify the "vertical" (nadir (-Y) and zenith (+Y)) axis of the build (relative to the floor in the VAB or SPH). If both -Y and +Y are used, then the origin is is ignored, otherwise the axis runs from -Y to origin or origin to +Y. NOTE: not recommended, very advanced usage.
- -Z and +Z used to specify the ventral(+Z)/dorsal(-Z) (VAB) or fore(+Z)/aft(-Z) (SPH) axis of the build. If both -Z and +Z are used, then the origin is is ignored, otherwise the axis runs from -Z to origin or origin to +Z.

* If none of the axis direction stakes are used, then the default orientation is such that the build's +Y axis is the local up, +X axis points east, and +Z points north (same as on the KSC launchpad).

- * If the axes marked out by the stakes are not perfectly orthogonal, then the build will be oriented such that the errors are balanced.
- **Bounds** these are used to control the placement of the build based on its bounding box rather than its root part.
 - **Origin** used to mark the location of the root part along any axis that has not been bound.
 - -X and +X used to mark the lateral (port (-X) and starboard (+X)) edges of the build. If only one of -X or +X is used, then that edge of the build will be exactly on that stake, otherwise the the X-axis center of the build's bounding box will be centered on the midpoint between the two stakes.
 - **-Y and +Y** used to mark the "vertical" (nadir (-Y) and zenith (+Y)) edges of the build. If only one of -Y or +Y is used, then that edge of the build will be exactly on that stake, otherwise the the Y-axis center of the build's bounding box will be centered on the midpoint between the two stakes. NOTE: use of the +Y bounds stake is not recommended unless you know what you are doing.
 - -Z and +Z used to mark the ventral(+Z)/dorsal(-Z) (VAB) or fore(+Z)/aft(-Z) (SPH) edges of the build. If only one of -Z or +Z is used, then that edge of the build will be exactly on that stake, otherwise the the Z-axis center of the build's bounding box will be centered on the midpoint between the two stakes.
- * Bounds stakes and direction stakes work together: any unbound axis of the build slides along that axis of the reference frame created by the direction stakes (or the default frame if no direction stakes are used).
- * There is actually only one origin stake: there is no difference between a bounds origin stake and a direction origin stake. The appearance of there being two origin stakes is due to the overly simple controls.
- * If multiple stakes of the same type+setting have been placed, then they will be averaged together to form a virtual stake of the same type+setting. This can be very

The VAB orientation really is weird. useful with multiple origin stakes to avoid the build clipping into the stake when the lowest part of the build is directly below the root part.

- * If no origin stakes have been placed, then the average of all other stakes is used as the origin point.
- * The actual location of the stakes is about 19cm above the ground.
- * If no Y bounds stake has been placed, then the origin acts as an implicit -Y bounds stake (otherwise almost all builds would spawn in the ground).

4. Designing a construction capable vessel

4.1. Orbital Construction

Orbital construction is probably the easiest to get going as all that is required is a supply of ROCKETPARTS, an orbital dock, some qualified construction kerbals, and somewhere for them to work. This means that only two parts need to be added to the design of a station that has crewed command pods or any stock crewed part¹⁹: a reasonably sized ROCKETPARTS container, and either the orbital dock or the micropad. When extending an existing station, a suitable docking port would be required as well, and means to get the "construction unit" to the station. However, if the micro-pad is used, then the micro-pad needs to be attached to the station somewhere using KISIgorZ n.d.(b). In fact, the micro-pad can be an excellent way of attaching an orbital dock to a station.

It can, however, be the most difficult to maintain due to the need for supplies to be flown to the station. That said, maintaining an orbital construction station can be quite interesting as there are a number of options for feeding ROCKETPARTS into the orbital dock's ravenous maw, each with additional design requirements for the station.

- Firstly, and most simply, ROCKETPARTS can be flown up from a nearby, or even not so nearby, production base²⁰. The only additional requirement for the station is an available docking port, but a station with no docking ports is of rather limited use, so this requirement is generally not too troublesome (though having enough docking ports on a station can be tricky at times).
- Secondly, METAL can be flown to the station and locally processed into ROCKETPARTS. Along with an available docking port, this

Figure 3: Orbital Dock



Figure 4: Micro-Pad

¹⁹there are mods that supply suitably configured crewed parts

²⁰The KSC counts as a production base as all EL resources can be loaded onto a vessel at launch time via tweakables.



Bounds stake, a +X Direction stake, a +Z Bounds stake with a +X Bounds stake hiding behind it, a flag and kerbal (not relevant to the site), and near the far right launch clamp, an Origin stake (direction, but bounds would have the same effect). This is one possibility for placing stakes for building a large structure on the side of a hill. From left to right, there's a -Y Although the top of the structure is not directly visible, it is horizontal. method requires a means of converting METAL to ROCKETPARTS. This can be done using either the workshop or the rocket workbench, but since even the rocket workbench can give a significant boost to production speed, the only real disadvantages are the relevant part needs to be either flown up to the station and docked or built at the station and maneuvered into a convenient location, and the increased power requirements. A minor disadvantage is the conversion of METAL into ROCKETPARTS produces SCRAP-METAL. Normally, the SCRAPMETAL is simply thrown away, but the next solution takes care of that.

- Thirdly, if METAL to ROCKETPARTS production is already available on the station²¹, a smelter can be added to the station allowing METALORE to be flown in and processed into METAL. While this does significantly increase the fuel requirements of the station, the smelter is actually dual-use: not only can it convert METALORE into METAL, but it can convert SCRAPMETAL into METAL, resulting in very low production losses. As an added bonus, the smelters have a small amount of storage for the three resources.
- Fourthly, and finally, a recycling bin can be added to the station. EL's recycling bins do not look like much, but they are ravenous maws that eat vessels of any size (except asteroids, but including unfortunate kerbals) and spit out resources. Most resources, except ABLATOR and SOLIDFUEL, stored in tanks will be reclaimed as-is without loss, and the hull material will be recycled into SCRAPMETAL. For best results, the station needs large quantities of storage and a full production chain. The biggest advantage of using a recycling bin is unmanned²² supply ships can be flown into the recycling bin and recycled. If there is sufficient storage on the station, then all remaining fuel and any stored resources will be automatically transfered to the station, and the hull of the supply ship will go towards the next construction project. Unfortunately, if there is insufficient storage for any resource, the the excess of that resource will be lost.

4.2. Grounded Construction

While more difficult to get going due to the need to fly to the location and land safely, grounded construction can be much easier to maintain as the site of the construction base can be chosen for optimal resource extraction. Thus once production facilities (as

The rocket workbench can be manhandled into position by two kerbals using KIS.

 $^{^{21}}$ Or is included in the same module as the smelter.

²²Or manned by very brave pilots.

described in the orbital construction section) are in place, the base can be self-sufficient for a very long time.

The main difference between orbital construction and grounded construction is that gravity can make getting built vessels off the pad rather awkward. Thus, instead of a launchpad, though launchpads can have their advantages (such as resource transfer), the base can be equipped with a survey station, a supply of survey stakes, a mallet to drive the stakes, and a KISIgorZ n.d.(b) container in which to store the stakes and mallet. As KIS is required for the survey parts to be available, the container should not be a problem²³.

4.2.1. The Base Kraken

One thing that makes base building particularly difficult is bases have a tendency to slide around on the ground, and even jumping into the air and possibly self destructing. None of this is helped by the difficulty of finding level ground anywhere but the flats of Minmus, and Minmus is so small that despite the flats being perfectly "flat"²⁴, the curvature is such that large sprawling bases have to bend to maintain contact with the ground, but generally will not due to Minmus' low gravity. Instead, they often tip slightly.

To solve the problem of bases sliding around, and in attempt to prevent them leaping into the air, various modes have implemented solutions involving attaching the base parts to the ground²⁵. However, stock KSP provides its own solution that EL's survey system enables: launch clamps. While launch clamps do have their disadvantages²⁶, they can turn a site that is untenable due to steep terrain into a stable and highly productive base: the root part is always level²⁷ with respect to the survey site's origin.

The above, both the ground anchoring done by other mods and the use of launch clamps, helps a lot in preventing bases from sliding around. Unfortunately, not so much when it comes to actually preventing a kraken attack on scene load. In fact, they can make things worse, for a rather counter-intuitive reason: the way KSP handles vessels going *on* rails (yes, on, not off). The reason these attempts to solve the base kraken can make things worse is that instead of the base being thrown away from the ground, it can be torn apart by the sometimes very violent forces that are attempting to throw the base.

As for KSP's handling of vessels going on rails...

KSP records the root-part relative positions and orientations of each part of the vessel. Normally, these never change²⁸.

When a vessel goes on rails, KSP snaps all parts back to their recorded positions and

 $^{^{23}\}mbox{Other}$ mods might provide alternative "stakes" with a different planting mechanism thus removing the need for KIS.

²⁴Flat Minmus Society, anyone?

 $^{^{25}\}mbox{Really},$ just to local space, but that's a minor technical PhysX detail.

 $^{^{26}\}mathrm{The}$ base can wind up quite high up from the ground.

 $^{^{27}\}mathrm{Unless}$ a Y direction stake is used.

²⁸Robotics parts do change them, and the vessel suffers for it over several save-load cycles.

orientations. This is readily seen when a wobbly wet-noodle rocket goes on rails²⁹: the rocket snaps straight.

For a grounded vessel, there are always sagging parts (some more, some less: depends on local gravity, part mass, joint spring strength³⁰, how far the part is from a more securely supported part, etc etc). Obviously, the sagging causes flexing. Thus when going on rails, the parts are snapped back to their recorded root-relative positions and orientations.

It is the position (and orientation) of the root part that determines the vessel's position etc when going on rails, and the vessel's position and orientation dictates the root part's position and orientation when going off rails.

Thus, when a ground base's root part sags, even though it may not look it, the whole base sags: when the base goes on rails, the base's location is determined by the root part, and all the supporting structure is snapped into position relative to that, resulting in the supporting parts being forced into the ground. Then, when the base goes off rails, the colliders of the support parts are in the ground and PhysX³¹ forces them out resulting in possibly extremely violent forces acting on the base, possibly throwing it away from the ground or even tearing the base apart.

Fortunately, the solution lies in the very cause of the problem, and is quite simple to implement.

- Keep the base segment containing the root part very light. This means no storage containers for anything massive.
- Give the root segment solid support such that it will not sag or even tilt. This is where the use of launch clamps really helps: they provide the needed support before physics is applied to the base.
- Keep massive storage in adequately supported separate base segments, connected to the root segment via relatively flexible lightweight connectors. The light weight prevents the connectors weighing excessively on the root segment, and the flexibility allows the massive segments to sag without dragging the root segment down with them. *This is not a problem, and is even desirable*: when the base goes on rails and KSP snaps the parts into position, the base segments will be snapped *away* from the ground instead of into it.
- Ensure that the root part of the base does not change.

The last is actually easier than it may sound: KSP has a priority system for determining which vessel is the "mother ship" (thus which root part remains root after coupling) when two vessels dock.

²⁹ie, entering time-warp, assuming time-warp can be entered and is not blocked by "vessel is under acceleration"

³⁰Not breaking strength.

³¹This is not a bug in KSP, Unity, or PhysX: no physics engine likes interpenetrating colliders, and most produce very non-physical forces in order to separate the colliders.

- vessel type Base > Station > Plane > Ship > Lander > Rover > Relay > Probe > Space Object (asteroid) > Debris.³²
- relative mass The vessel with the greater mass becomes the "mother ship". For otherwise identical ships, resource loads will make a difference.
- vessel id While the order may appear random, it will be consistent, but the mass tolerance is pretty tight, so this is pretty rare.

Thus, if the root segment is made a base early on, it *should* remain the root throughout the life of the base unless the base is connected to a more massive base (at the time of connection).

4.3. Roughing It

This is grounded construction the hard way³³. The absolute minimum is flown to a site and the first things constructed are the modules needed to sustain construction.

Parts and resources to be flown in:

- Suvery Station Needed to do the building on the marked site. This doubles as a workshop, though productivity is poor.
- Survey Stakes Needed to mark where to build.
- Mallet Needed to drive the stakes.
- **RocketParts** Only a very small quantity is needed: 3.5328t is the minimum, though a little more is recommended.
- **KASIgorZ n.d.(a)** Pipe Connectors Needed to attach the build modules to allow resource transfer.
- **KISIgorZ n.d.(b) Screwdriver** While the wrench may be sufficient for attaching pipe connecters, the screwdriver is more versatile.

Modules to be built first:

- **Tiny Auger** 0.5328t This is the smallest auger supplied by EL. Needed to extract MetalOre.
- **Tiny Smelter** 1.5t This is the smallest smelter supplied by EL. Needed to convert MetalOre to Metal.

 $^{^{32}\}mathrm{Docking}$ a station to a base... neat trick. ³³My preferred way.

Rocket Workbench 1.5t While this is needed for converting Metal to RocketParts, it is also a fully equipped workshop with room for four kerbals. Once this is built, construction kerbals can be moved from the survey station to the workbench, significantly increasing productivity and thus allowing later builds to progress at a faster rate.

Once the required modules have been built, base production can go into full swing, even the construction of larger resource production chain, including recycling and the full-sized workshop.

Part II. Modding Extraplanetary Launchpads

5. Configuration

5.1. Part Modules

For the most part, EL places no restrictions on the models used for parts using EL's module, so unless otherwise stated, models are completely free-form as far as EL is concerned.

5.1.1. ELControlReference

Allows the part to become a control reference ("Control From Here" in the part's PAW). Also provides a "Toggle Reference" action group that saves the previous control reference when becoming the reference and returns the vessel to the previous reference when toggled again.

Model Requirements The model's mesh needs an emissive material with _EmissiveColor set with appropriate RGB values. The alpha value is used for turning the emission on and off as a status indicator. The part's root game object is used as the reference transform consistent with command pods and docking ports, so the model should be shaped appropriately.

Part Requirements None

Module Fields None

5.1.2. ELConverter

Consumes a set of input resources to produce a set of output resources. An EL converter uses a converter recipe (see 5.2.3 on page 35) to specify the inputs and outputs while





controlling the rate of flow of the resources specified by the active input recipe and distributing the recipes specified by the active output recipe. The active input and output recipes are selected by the current efficiency of the converter, and may be a blend between two specified recipes. The efficiency of the converter is either fixed, or determined by the temperature of the converter part.

ELConverter subtracts the total input heat from the part and adds the total output heat to the part (use negative heats to have heating associated with input ingredients and cooling with output ingredients).

If an efficiency curve³⁴ has been specified, then the converter's efficiency is determined by the part's internal temperature (otherwise the efficiency is constant). The converter's efficiency is then used to bake the converter recipe into a specific conversion recipe.

Once the specific conversion recipe has been obtained, **ELCONVERTER** then bakes that recipe using the current mass flow rate. The current mass flow rate is the specified rate of the converter scaled by the relative mass of the active input recipe compared to the smallest mass input recipe in the converter recipe. This keeps the mass flow of certain resources constant while varying the flow of others appropriately³⁵ when suitable ratios are specified. The mass flow rate of the output recipe is always the same as that of the input recipe³⁶.

Model Requirements None

Part Requirements None. However, it is strongly recommended to use appropriate significant thermal settings for converters that use heat. In particular, skinInternalConductionMult thermal flux and heatConductivity should be adjusted to provided sufficient insulation when keeping the part hot is necessary.

Module Fields

EVARange Adjust the range (in meters) from which an EVA kerbal can activate or deactivate the converter. Default is 1.5m.

ConverterRecipe The name of the converter recipe to use. Required.

- **Rate** The base mass flow rate of the converter, in kg/s. Defaults to 0. The base mass flow rate is that of the smallest mass input recipe in the converter recipe.
- efficiency Specify the efficiency/temperature curve of the converter. Defaults to constant 1.0 (100%). If a single efficiency entry is given, then it specifies a constant efficiency and is of the form efficiency = 0.9 (90%). If multiple EFFICIENCY entries are given, then they form keys in a piece-wise linear "curve". Each entry is

Note that KSP's thermal data in the PAW does not directly show the effects of resource transfer on the part's temperature, there \mathbf{SO} be may significant despite the temperature being fairly stable.

³⁴For certain values of "curve": it's piece-wise linear.

 ³⁵For example, in a smelter, LIQUIDFUEL and OXIDIZER flow at a constant rate, while METALORE is not consumed at all at 0% efficiency, but is consumed at the maximum rate at 100%. Thus the actual mass flow rate might vary from 864.49048g/s to 2461.37248g/s.

 $^{^{36}\}mathrm{Conservation}$ of mass.

of the form efficiency = temp, eff where temp is the part's internal temperature in Kelvin and eff is the converter's efficiency at that temperature. Note that the keys need to be specified in ascending order of temperature and eff should be between 0.0 and 1.0 (inclusive)³⁷. For temperatures outside the range of the curve, the nearest key is extrapolated with a constant efficiency.

5.1.3. ELDisposablePad

Special one-shot launchpad that replaces itself with the built vessel, attaching the built vessel to the vessel owning the pad.

Model Requirements The only requirement is the model provides a transform with the up axis (positive Y-axis in KSP/Unity, Z-axis in Blender) pointing *away* from where the spawned vessel will be as it will be used to align the selected attach node of the vessel's root part. This is the opposite direction of the transform used by ELLaunchpad. Also note that the position of the selected attach note will match the position of the transform, so for a flush fit, the transform should be at the same position as the pad's attach node³⁸.

Part Requirements None.

Module Fields

- **SpawnTransform** Specifies the model transform to be used as the launch transform. Optional, but using a spawn transform makes the virtual attach node independent of the part's transform.
- **PadName** Specifies the name of the launchpad. Note that this is editable by the user both in the editor (VAB/SPH) or in flight.

Operational Persistent backing for ELControlInterface.canOperate. Defaults to true.

5.1.4. ELExtractor

Extracts resources from the environment. Note that ELExtractor works with both the stock resource system and with Kethane (auto-detected if installed). Can (with a little work³⁹) be extended to support other resource providers. All supported providers are treated equally in that the amount of resource extracted from a provider is based on that provider's contribution to the available resource at the location of extractor part's ground-hit location. For example with Kethane installed, EL's auger will extract

 $^{^{37}\}mathrm{No}$ checking is performed, so expect rhinodaemons should this rule be broken.

 $^{^{38}\}mathrm{Rodger:}$ basically it should replicate the attach node of the spawned craft, pointing towards the mothership, and on the point where the motherships node was

³⁹Currently, this would require modifying EL's source to search for implementers of IResourceProvider instead of simply adding the stock and Kethane (if installed) providers.

METALORE from a Kethane deposit at a rate slightly lower than specified by **Rate** in the module files because the stock resource system will provide a certain amount (based on concentration) as well, resulting in the total rate of extraction being as specified, but if the auger misses a Kethane-based deposit, the extraction rate will be determined by concentration multiplied by the specified rate.

Model Requirements ELExtractor requires the model to have a head transform (goes into the ground) and a tail transform (does not go into the ground). The transforms are used to do a physics ray-cast to determine both whether the extractor has ground contact and the exact location of that contact. The head transform must be outside any colliders in order to allow it into the ground (visual mesh that penetrates the ground poses no problem). The tail transform may be either inside or outside any colliders, but inside is recommended to ensure that it cannot go into the ground. The transforms may be animated: the ray-cast is performed each frame.

Part Requirements None.

Module Fields

- **EVARange** Adjust the range (in meters) from which an EVA kerbal can activate or deactivate the extractor. Default is 1.5m.
- **ResourceName** The name of the resource to extract. Required.
- **Rate** The flow rate of the extractor, in u/s (resource units/second). Defaults to 0.
- **flowMode** How the extracted resource is distributed through the extractor vessel. Defaults to ALL_VESSEL.
- **HeadTransform** The name of the model transform used as the target of the ray-cast used to detect ground contact. This is the point of the model that needs to be in the ground for the part to be considered in contact with the ground.
- **TailTransform** The name of the model transform used as the source of the ray-cast used to detect ground contact. This is the point of the model that needs to be out of the ground for the part to be considered in contact with the ground.
- INPUT_RESOURCE{} Note that this is a node. This is as per the stock resource extraction module (ELExtractor is derives from BaseDrill, so many of BaseDrill's fields and nodes are relevant).

5.1.5. ELLaunchpad

Builds complete vessels attached (pseudo-docked) to the current vessel. Allows postbuild resource transfer without any extra fuss. Supports building both landed or in orbit. **Model Requirements** No requirements, but it is highly recommended that the part has plenty of free space "above" (positive Y-axis in KSP/Unity, Z-axis in Blender) the launch transform.

Part Requirements None.

Module Fields

- **SpawnHeightOffset** Specifies the distance in meters above the launch transform of the lowest point of the spawned vessel. This is most useful when the model does not have a specific spawn transform. Defaults to 0.0m.
- **SpawnTransform** Specifies the model transform to be used as the launch transform. Optional, but using a spawn transform allows finer control over the launch position than that afforded by SpawnHeightOffset, and also allows the orientation to be specified. If not specified, the model's root transform will be used as the launch transform (setting SpawnHeightOffset is highly recommended, but not as highly as having a spawn transform).
- **PadName** Specifies the name of the launchpad. Note that this is editable by the user both in the editor (VAB/SPH) or in flight.

Operational Persistent backing for ELControlInterface.canOperate. Defaults to true.

5.1.6. ELNoControlSwitch

Resets the vessel's control reference to what it was before a kerbal boards the external command seat. Used by the rocket workbench to prevent the vessel getting weird control references⁴⁰.

Model Requirements Somewhere for a kerbal to sit.

Part Requirements At least one KERBALSEAT module.

Module Fields None.

5.1.7. ELRecycler

Destroys anything it touches (including unfortunate kerbals), reclaiming what resources it can. Implements ELControlInterface.

Model Requirements The only requirement is the recycle field. The recycle field must be a trigger collider and should (must?) not touch any other collider.

⁴⁰Imagine how annoying this can be when using SAS hold option on a bendy station. Now imagine the motivation for creating this part module.

Part Requirements None.

Module Fields

RecycleField_name Specifies the name of the transform for the recycle field collider. Defaults to "ReycleField".

RecycleRate Specifies the recycling rate in tons/second. Defaults to 1.0t/s.

Operational Persistent backing for ELControlInterface.canOperate. Defaults to true.

5.1.8. ELSurveyStake

Marks locations for survey station. In the current implementation, a stake must be the only part in the vessel for the survey station to recognize it.

Model Requirements None except any required by KISIgorZ n.d.(b) for ground attachment.

Part Requirements As the survey system will not look at vessels with more than one part to check for the ELSurveyStake module, the part should be configured to be ground attached using KISIgorZ n.d.(b). However, parts designed to be dropped via staging or decoupling will work, too, so long as the resulting vessel consists of only the one part.

Module Fields None.

5.1.9. ELSurveyStation

Builds complete vessels at locations marked out using survey stakes (parts with the ELSurveyStake module). Does not allow post-build resource transfer (freedom is not free), but as KISIgorZ n.d.(b) is required to place the stakes, and KASIgorZ n.d.(a) is almost always installed with it, survey stations are probably the preferred tool for landed operations. Implements ELControlInterface.

Model Requirements None.

Part Requirements No requirements, but as kerbals improve its range, having crew capacity (crewCapacity > 0 or KerbalSeat modules) is recommended.

Module Fields

StationName Specifies the name of the survey station. Note that this is editable by the user both in the editor (VAB/SPH) or in flight.

Operational Persistent backing for ELControlInterface.canOperate. Defaults to true.

SiteRanges Comma separated list of skill based ranges (in meters) for the survey station. If not provided, the defaults will be used. Excess ranges are ignored, insufficient ranges result in unspecified ranges being left as default. Zero or negative ranges leave that range at the default value. Errors simply abort the processing of the list and are equivalent to the list being short (but a error is sent to KSP.log).

5.1.10. ELTarget

Allows a part to be targeted. Includes orientation so it works with any docking alignment mod (DPAINavyFish n.d., navballlinuxgurugamer n.d., and navhudNinenium n.d. are known to work).

Model Requirements None.

Part Requirements None.

Module Fields

- **TargetTransform** Specifies the model transform to be used as the target. If not specified (the default), the model's root transform will be used.
- **TargetName** String to be added after the host vessel's name when set as target. Defaults to "Target".

5.1.11. ELWorkshop

Collect productivity from kerbals in the part. Works with either normal parts with crew capacity or command chairs.

Model Requirements None.

Part Requirements The part must have some crew capacity. This can be via either the part's crewCapacity field, or KerbalSeat (stock KSP) modules, or both. Note that parts may have multiple KerbalSeat modules on them (eg, EL's Rocket Workbench).

Module Fields

- **ProductivityFactor** Specifies the multiplier for calculating kerbal productivity. Must be greater than 0. All workshops with **ProductivityFactor** greater than 1.0 are considered to be fully equipped (ie, even 0-star kerbals with the construction skill can contribute). Defaults to 1.0.
- **UnmannedProductivity** Productivity of the workshop when unmanned. Not affected by ProductivityFactor. Defaults to 0.0.

- **FullyEquipped** If true, then even workshops with productivity factors less than 1.0 are considered fully equipped allowing 0-star kerbals to contribute.
- **IgnoreCrewCapacity** If true, the workshop will operate even if the part's **crewCapacity** is 0 (and not check for **KerbalSeat**). This is most useful on parts with dynamic crew capacities (eg, inflatables).

5.2. Recipes

Extraplanetary Launchpads provides, via recipes, a means of customizing the resource costs for building parts, their modules and resources, and thus whole vessels. The recipes are used also for recycling.

Essentially, recipes are config nodes with a list of ingredients with their ratios in the form of INGREDIENTNAME = RATIO, although each recipe type will be a little more complex (details given below). The final ratio of each ingredient is calculated by dividing the specified ratio by the sum of the ratios of all ingredients in the recipe such that the final total is 1.0. This allows for flexibility in how the ratios are specified, so long as consistency is maintained throughout the individual recipe: they can be considered as "parts" as in when mixing drinks (one part this, two parts that...), as masses in any unit (24g this, 16g that, 6g the other⁴¹), percentages (if they add up to 100), or raw ratios (if they add up to 1.0). Note, however, that EL always uses mass for its calculations.

For example, glucose $(C_6H_{12}O_6)$ using approximate molar masses:

Using masses:	Using parts:	Using raw ratios:
Carbon = 72	Carbon = 6	Carbon = 0.4
Hydrogen = 12	Hydrogen = 1	Hydrogen = 0.06667
Oxygen = 96	Oxygen = 8	Oxygen = 0.53333

In general, the ingredients will be KSP resources. EL looks up the resource to find its density and calculates the amount of resource required based on the total mass of the recipe, the ingredient's ratio within the recipe as a fraction of the total mass, and the density of the resource to give the resource units required to achieve that mass.

Ingredients may be repeated within a recipe, in which case their ratios will simply be added together. This makes creating recipes from chemical formula a little easier.

Unknown ingredients contribute to the total ratio and thus affect the ratios of known ingredients. Their effects when building are undefined, but they operate as losses when recycling (i.e., unknown ingredients simply evaporate when a part is recycled).

Ingredients specifying KSP resources that have no mass do not contribute their ratios to the recipes total, but will be scaled by the same amount as the ingredients that do have mass. Unknown ingredients are assumed to have mass. A recipe consisting of only ingredients that have no mass will cause headaches.

 $^{^{41}\}mathrm{A}$ popular compound.

5.2.1. Recipes for Building

Building parts (and thus vessels) requires resources. The total mass of the resources required for building a part is given by the part's mass, but the mix of resources needed by the part is given by the part's recipe. Also, certain resources stored in a part (e.g. SOLIDFUEL, ABLATOR) cannot normally be created by other means (neither stock ISRU nor Kethane provide a means to produce them), nor can they be transfered, so recipes can be used for specifying how to build them.

Any resource listed in a recipe becomes a required resource (i.e. the build will not complete if any required resource runs out). Note, however, that normal resources that are simply stored in the part to be built remain optional. For example, to build a tank that holds ROCKETPARTS, A mass of ROCKETPARTS equivalent to the dry mass of the tank is required to build the tank itself, but the ROCKETPARTS used to fill the tank remain optional. Thus, if there is a supply of ROCKETPARTS sufficient to build the tank, but not enough to fill it, then the tank will be only partially full (or possibly even empty) when built.

In summary:

- Any resource mentioned in EL_Recipe or EL_ModuleRecipe is required for building (but not for filling tanks).
- Any stored resource that has an EL_ResourceRecipe becomes a required resource (eg, SOLIDFUEL).
- Any resource stored in a part inside a KIS container becomes a required resource, regardless of recipes.
- **EL_Recipe** Specify the resources needed to build a part. **EL_Recipe** is to be added to the part's config (either by hand or using Module Manager). **EL_Recipe** nodes are really two nested recipes: the outer recipe specifies the ratios between the part's structure (using **structure** as the ingredient name) and its part modules (the ingredient name is the name of the part module). The inner recipe is the **Resources** node, which specifies the resources needed to build the part's structure.

Any part that does not have an EL_Recipe node will be given the default shown below, but with additional modulename = 1 lines for each part module on the part that has a corresponding EL_ModuleRecipe. Also, the Resources node will be taken from EL_DefaultStructureRecipe (both for parts that have no EL_Recipe node, or whose EL_Recipe node has no Resources node).

```
EL_Recipe {
    structure = 5
    Resources {
        RocketParts = 1
    }
}
```

EL_ModuleRecipe Specify the resources needed to build any part's module. Applies to all instances of that module. The module to which the recipe applies is specified by the name = line, and the actual recipe for the module is specified by the Resources node. The mass of the module is calculated from the part's mass using the ratio specified in the part's recipe. If the named module does not exist, no module is named (ie, no top-level name = line), or no recipe is given (no Resources node), the recipe will be dropped from the recipe database.

The example below gives EL's module recipe for KerbalEVA. The ratios are in kilograms, assuming a suited kerbal has a mass of 93.75kg (10kg for the kerbal). It can be found in Kerbal.cfgtaniwha n.d.(c).

```
EL_ModuleRecipe {
    name = KerbalEVA
    Resources {
        Metal = 39
        loss = 44.75
    }
}
```

EL_DefaultStructureRecipe Specify the default recipe to be used for a part's structure when the part has no recipe or the recipe does not specify a recipe for its structure. There is no node in EL's configs: it is hard coded. However, providing an EL_DefaultStructureRecipe will override the hard-coded default.

```
EL_DefaultStructureRecipe {
    RocketParts = 1
}
```

EL_ResourceRecipe Specify the resources needed to "build" a resource. The resource to be "built" is specified by the name = line, and the recipe for the "built" resource is specified by the Resources node. If no resource is named (ie, no top-level name = line), or no recipe is given (no Resources node), the recipe will be dropped from the recipe database. Recipes for undefined resources are permitted, allowing for resource "macros"⁴². The example resource recipe shows ABLATOR being made from ROCKETPARTS. It and a similar recipe for SOLIDFUEL can be found in Recipes.cfgtaniwha n.d.(d).

```
EL_ResourceRecipe {
    name = Ablator
    Resources {
        RocketParts = 1
    }
}
```

 $^{42}\mathrm{TODO:}$ In theory: not tested.

5.2.2. Recipes for Recycling

First off, when recycling, part recipes (EL_Recipe) are used for breaking a part down into its constituent resources. Whether from breaking down the part or "drained" from the part's resource storage, any resource that has a resource recipe (EL_ResourceRecipe) will simply evaporate. However, if the resource has a recycle recipe (EL_RecycleRecipe), then that recipe will instead be broken down to the resources specified by the recycle recipe. A transfer recipe (EL_TransferRecipe) is used to force a stored resource that would otherwise be lost or broken down by a recycle recipe to be transfered.

- Any resources stored in the part are drained. Those with an EL_TransferRecipe are transferred accordingly. Those with an EL_ResourceRecipe but no EL_RecycleRecipe are lost, otherwise they are broken down as dictated by the EL_RecycleRecipe and the resultant resources will be transfered.
- The part is then broken down into the resources specified by its EL_Recipe and EL_ModuleRecipe(s). Those resources with an EL_ResourceRecipe but no EL_RecycleRecipe are lost, otherwise they get broken down further in accordance with their EL_RecycleRecipe.
- Whether transferring (from a tank) or recycling (the part itself), resources with no recipe are reclaimed as-is at a 1:1 ratio.
- EL_RecycleRecipe Specify the resources to which a resource will be broken down when recycling. Prevents evaporation of the resource when the resource has a resource recipe (EL_ResourceRecipe). The resource to be broken down is specified by the name = line, and the recipe for the broken down resource is specified by the Resources node. If no resource is named (ie, no top-level name = line), or no recipe is given (no Resources node), the recipe will be dropped from the recipe database. Ingredients specifying undefined resources are permitted, allowing for loss ratios to be specified. The example recycle recipe shows ROCKETPARTS being broken down to SCRAPMETAL with 10% loss (the exact name (loss) doesn't matter so long as it is not a defined resource). It can be found in Recipes.cfgtaniwha n.d.(d).

```
EL_RecycleRecipe {
    name = RocketParts
    Resources {
        ScrapMetal = 9
        loss = 1
    }
}
```

EL_TransferRecipe Specifies how a resource that was stored in a part is to be transfered. Prevents the resource from being broken down by a recycle recipe when being drained from a part's storage. The resource to be transfered is specified by the name = line, and the recipe for the transfered resource is specified by the Resources node. If no resource is named (ie, no top-level name = line), or no recipe is given (no **Resources** node), the recipe will be dropped from the recipe database. Recipes for undefined resources are permitted, allowing for loss ratios to be specified. In general, the same resource should be specified in the recipe, but a transfer recipe can be used for converting a resource that does not have a recycle recipe, or for specifying a loss factor while transferring. The example transfer recipe shows ROCKETPARTS being transfered without any loss or conversion. It can be found in **Recipes.cfg**taniwha n.d.(d).

```
EL_TransferRecipe {
    name = RocketParts
    Resources {
        RocketParts = 1
    }
}
```

EL_KerbalRecipe Specifies the resources making up a kerbal (whether on EVA or boarded⁴³). This is a special part recipe that is not actually attached to any part⁴⁴, and is used only when the unfortunate kerbal gets recycled. The kerbal recipe shown below assumes a fully suited kerbal is 93.75kg (the default in KSP) with 10kg for the kerbal and 83.75kg for the suit, with a $30:1 \ gain^{45}$ when converting the kerbal to KETHANE. It can be found in Kerbal.cfgtaniwha n.d.(c).

```
EL_KerbalRecipe {
    structure = 10
    KerbalEVA = 83.75
    Resources {
        Kethane = 30
        loss = -29
    }
}
```

5.2.3. Recipes for Converting

EL_ConverterRecipe Conversion recipes make configuring chemically correct⁴⁶ resource converters fairly simple as they allow the conversion rate to be separated from the resource ratios. Each conversion recipe provides a name which can be referenced by the converter config, a set of input recipes, and a set of output recipes. At least one of each recipe set must be present for the converter recipe to be valid, but there is no need for the two sets to have the same number of recipes.

 $^{^{43}\}mathrm{The}$ kerbal is assumed to be suited or have a suit nearby in the same part

⁴⁴The need for the node came from not having access to KerbalEVA part configs at the time, and keeping it after KSP 1.2 maintains flexibility.

 $^{^{45}{\}rm Highly}$ unrealistic, but that is how the KE-WAITNONOSTOP-01 in Kethane is configured $^{46}{\rm Or}$ reasonable approximations thereof.

All ingredients in an input recipe must be either a defined KSP resource, or an EL_RESOURCERECIPE. Any ingredients in a referenced EL_RESOURCERECIPE also must be defined. In the example below, LFOMIX is such. It is used because stock KSP LIQUIDFUEL and OXIDIZER densities are incorrect for RP-1 (0.81kg/L) and LOX (1.141kg/L) which makes getting the rates correct difficult. Thus LFOMIX is a workaround.

Any undefined ingredients in an output recipe simply evaporate (i.e., they are jettisoned).

Both input recipes and output recipes have a special ingredient: EFFICIENCY. The EFFICIENCY ingredient is used to calculate the actual recipe used by the converter based on the converter's current efficiency, acting as keys in an efficiency curve. The ratios of the other ingredients are interpolated between those specified by the recipes with efficiencies on either side of the converter's current recipe. Ingredients in converter recipes support an optional heat parameter which defaults to 0 and is scaled with the ingredient when the recipe is baked. Output heats are added to the part's internal flux while input heats are subtracted from the part's internal flux. If the ingredient ratios are in grams, then the heats are in kilo-joules. The mass flow of the conversion process is governed by the input recipe with the smallest mass.

```
EL_ConverterRecipe {
```

```
name = LFOFiredSmelter
Input {
    efficiency = 1
    LFOMix = 864.49048 -5186.94288
    MetalOre = 1596.882
}
Output {
    efficiency = 1
    CarbonDioxide = 1056.228
    Water = 288.24448
    Metal = 1116.9 -9627.678
}
Input {
    efficiency = 0
    LFOMix = 864.49048 -5186.94288
}
Output {
    efficiency = 0
    Carbon = 24.0214
    CarbonDioxide = 176.038
    CarbonMonoxide = 476.1717
    Formaldehyde = 30.02598
```

```
Hydrogen = 14.11116
Water = 144.12224
}

EL_ResourceRecipe {
    name = LFOMix
    Resources {
        LiquidFuel = 9
        Oxidizer = 11
    }
}
```

5.2.4. Other Recipes

EL_ResourceLink While not strictly a recipe, EL_RESOURCELINK is used for specifying resources that should be linked when setting up resource transfer after building a new craft but before releasing it. The node is very simple: a **name** line that names the link set (currently not used internally, but useful for Module Manager patches), and a series of **resource** lines that specify the resources in the link set. Any link sets with overlaps in their linked resources will result in undefined behavior⁴⁷

```
EL_ResourceLink {
    name = RocketFuel
    resource = LiquidFuel
    resource = Oxidizer
}
```

5.3. Resource Rates

The amount of work required to prepare resources may be configured using an EL_ResourceRates node. This node is very simple in that it is just a list of resourcename = rate lines. resourcename is the name of the resource (or default to specify the default rate), and rate is the amount of kerbal-hours / ton (or kerbal-seconds / unit for massless resources (such as ELECTRICCHARGE)). Note that this affects only those resources that are required to complete the build, not optional resources that will be transferred afterwards. If default is not specified, then it defaults to 5.

```
EL_ResourceRates {
    default = 5
    ElectricCharge = 1
    LiquidFuel = 0.36
    Oxidizer = 0.44
```

⁴⁷rhinodamons

```
MonoPropellant = 0.4
XenonGas = 2
Ore = 8
}
```

6. EL API

Calling it an API might be stretching things, but...

6.1. Interfaces

6.1.1. ELBuildControl.IBuilder

ELBuildControl is the actual workhorse for building vessels, the various pad modules all use ELBuildControl for the common functionality. The IBuilder interface is the methods and properties that ELBuildControl requires of the pad modules. There are several methods and properties, but main property of interest is CONTROL which provides access to the ELBuildControl object attached to the pad.

6.1.2. ELControlInterface

Its purpose is to allow other mode easy control and detection of the operational status of EL's modules. For example, mode with inflatable parts can disable the EL module when the part is deflated and block deflation when the EL part is busy.

Fields Note that these are actually properties, so access via reflection needs to be done using GetProperty, PropertyInfo.GetValue and PropertyInfo.Setvalue.

- **isBusy** Read-only boolean that indicates whether the module is currently busy processing something. While not enforced, the module should not be disabled while it is busy (i.e. the part should not be deflated).
- **canOperate** Boolean usable by other part modules to enable or disable (or detect) the operational status of the EL part module. Setting this may cause the implementing module to run other code (e.g. the ELSurveyStation module will recompute its range and possibly scan for sites), so mods must invoke the property setter to guarantee correct behavior.

6.1.3. ELWorkNode

Base interface for ELWorkSink and ELWorkSource. Any module implementing ELWorkNode will have its workNet property set by ELVesselWorkNet when the network is updated.

6.1.4. ELWorkSink

Consumes vessel productivity to get something done.

6.1.5. ELWorkSource

Provides vessel productivity.

6.1.6. IResourceProvider

Interface used by **ELExtractor** for querying environmental resource availability and extracting a resource from the environment.

6.2. Part Modules

- 6.2.1. ELControlReference
- 6.2.2. ELConverter
- 6.2.3. ELDisposablePad
- 6.2.4. ELExtractor
- 6.2.5. ELLaunchpad
- 6.2.6. ELNoControlSwitch
- 6.2.7. ELRecycler
- 6.2.8. ELSurveyStake
- 6.2.9. ELSurveyStation
- 6.2.10. ELTarget
- 6.2.11. ELWorkshop
- 6.3. Vessel Modules

6.3.1. ELVesselWorkNet

Central control of productivity for the entire vessel. Keeps track of output from work sources (eg, workshops) and distributes the productivity over active work sinks (eg, pads). Operates on unloaded vessels as well as loaded vessels so that work is properly distributed when multiple work sinks are operating but they finish at different times while the vessel is unloaded. Also prevents erroneous productivity credit caused by leaving a vessel unattended for several game years⁴⁸.

⁴⁸Background building was implemented by keeping track of how long the vessel was unloaded. When the vessel was loaded, the time was processed in chunks of (default) 21600 seconds every physics frame. This works out to fifty Kerbin days per second, so if a vessel had not been visited for ten Kerbin years, there would be an 85 second (game-time, worse for low FPS real-time) window after switching to the vessel in which new builds would finish instantly (assuming resource availability).

References

- 5thHorseman. KSP Bases 0.90 29: Ike ELP Base: Check! 5th Horseman Let's Play. URL: https://www.youtube.com/watch?v=67vth86RQH0&t=1525.
- [2] Angel-125. *Pathfinder*. URL: http://forum.kerbalspaceprogram.com/index. php?/topic/121397-pf/.
- [3] blizzy78. Toolbar. URL: http://forum.kerbalspaceprogram.com/index.php? /topic/55420-tb/.
- [4] IgorZ. Kerbal Attachment System. URL: http://forum.kerbalspaceprogram. com/index.php?/topic/142594-kas/.
- [5] IgorZ. Kerbal Inventory System. URL: http://forum.kerbalspaceprogram.com/ index.php?/topic/149848-kis/.
- [6] linuxgurugamer. Navball docking alignment indicator (Community Edition, v2). URL: http://forum.kerbalspaceprogram.com/index.php?/topic/152739navball/.
- [7] NavyFish. *Docking Port Alignment Indicator*. URL: http://forum.kerbalspaceprogram. com/index.php?/topic/40423-dpai/.
- [8] Nils277. Kerbal Planetary Base Systems. URL: http://forum.kerbalspaceprogram. com/index.php?/topic/133606-kpbs/.
- [9] Ninenium. NavHud a NavBall inspired Heads Up Display. URL: http://forum. kerbalspaceprogram.com/index.php?/topic/73692-navhud/.
- [10] H.W. Paxton R.J. Fruehan O. Fortini. "Theoretical Minimum Energies To Produce Steel." In: ().
- [11] rabidninjawombat. ExtraPlanetary LaunchPads Extended-Part Pack. URL: http: //forum.kerbalspaceprogram.com/index.php?/topic/80988-elkarb/.
- [12] RealGecko. Simple Construction. URL: http://forum.kerbalspaceprogram.com/ index.php?/topic/152575-sc/.
- [13] Sarbian. Module Manager. URL: http://forum.kerbalspaceprogram.com/ index.php?/topic/50533-mm/.
- [14] taniwha. Diamond Grid Trusses and Containers. URL: https://forum.kerbalspaceprogram. com/index.php?/topic/180255-dg/.
- [15] taniwha. Extraplanetary Launchpads. URL: http://forum.kerbalspaceprogram. com/index.php?/topic/54284-el/.
- [16] taniwha. ExtraplanetaryLaunchpads/Resources/Kerbal.cfg.
- [17] taniwha. ExtraplanetaryLaunchpads/Resources/Recipes.cfg.
- [18] taniwha. KerbalStats. URL: http://forum.kerbalspaceprogram.com/index. php?/topic/89285-ks/.
- [19] taniwha. Kethane. URL: http://forum.kerbalspaceprogram.com/index.php? /topic/119480-kethane/.

- [20] taniwha. Modular Fuel Tanks. URL: http://forum.kerbalspaceprogram.com/ index.php?/topic/58235-mft/.
- [21] taniwha. *Talisar Parts.* URL: http://forum.kerbalspaceprogram.com/index. php?/topic/116849-tp/.
- [22] TriggerAu. Kerbal Alarm Clock. URL: http://forum.kerbalspaceprogram.com/ index.php?/topic/22809-kac/.
- [23] Z-Key Aerospace. *TAC Fuel Balancer*. URL: http://forum.kerbalspaceprogram. com/index.php?/topic/139223-tacfb/.